

IOWA STATE UNIVERSITY

R2U2 Demo (Jan.2018) Documentation

January 1, 2018

QUICK DEMO SETUP

System input: combined sensor data in binary format

System output: verdict and time stamp for each future time monitor assembly instruction

1 Brief Setup Process

This section talks about how to generate required files and steps to run the demo.

Note: 1) The text mark with means the command typed in terminal.

2) The text marked in green are the files that require manually modify.

1.1 Preprocessing

1. Generate checker associated file
 - (a) Modify `inputs.py` (section 2.1) to specify the input data format and name, then run `python inputs.py`
 - (b) Generate `at_checkers.vhd` and `log_input_pkg.vhd` by running `python transformer.py`
 - (c) Write atomic assertion configuration in `input.ast` (section 2.2), run `python assert_convert.py` to convert the assertion into binary configuration file named `res.atc`.
2. Generate binary instruction assembly code and its interval file (.imem and .int)
 - (a) write assembly code in `casestudy.ftasm`, run `sh convert.sh` in folder
3. Generate UART byte data
 - (a) Modify parameters associated with data byte size in `python gen_uart_data.py` (section 2.3). These parameters should be the same as `R2U2_pkg.vhd`. Run command `python gen_uart_data.py`

1.2 Hardware Connection

1. FPGA Board Connection
 - (a) Connect the JTAG with PC for downloading bitfile. See Figure 1.
2. UART Connection
 - (a) Connect the UART module with PC, connect UART module PIN **DIN** with Zedboard **JP4**, PIN **DOUT** with Zedboard **JP3**. See Figure 2.
3. Reset button is located in Zedboard **BTNC(P16)**.

1.3 Run

1. Download bitfile into FPGA
2. Modify `ser.py` (section 2.4) to specify the correct uart port on PC and .dat byte size (should be the same size as in `R2U2_pkg.vhd`).
3. Run `sudo python ser.py`. This script will send atomic checker's and future time monitor's configuration to the board automatically.
4. Type binary data as input (same format as each line in `logged_data.dat`) and press enter. You will see the result displayed in the terminal window.

Figure 1: Zedboard connection setup





Figure 2: UART module connection setup



2 Details of Scripts and Files

2.1 inputs.py

(only compatible with python 2.x)

Processing raw data file (similar to .csv) to the data format we want.

Parameters and functions:

1. DATA_SET: Raw data set file

2. class subclass(CsvParser):
e.g.

```
class Gs111m(CsvParser):
    def __init__(self):
        CsvParser.__init__(self)
        self.file = DATA_SET + "/gs111m_0.csv"
        self.addConfig(9, "float", 10, 24, "roll_angle", "in_1/2^10_rad")
        self.addConfig(8, "float", 10, 24, "pitch_angle", "in_1/2^10_rad")
```

Comment: Create a subclass. It will subtract the data you mentioned in **self.addConfig** and output the processed data into **self.file** The self.file will look like:

roll_angle	pitch_angle
-42	12
-34	6
-25	3
...	...

▷ self.addConfig(channel, type, comma, width, name, comment)

@ channel: Column of the data in the raw data file.

@ type: Float or not. If it's float, write "float", else leave null.

@ comma: Only used for floating data type. It specifies how many fraction bit in binary you want to reserve during the conversion.

@ width: Number of bits for this data.

@ name: Specify the name of the column data. This will affect the name used in the .vhd code.

@ comment: Add any comment in string as you want.

3. class subclass(AtChecker):
e.g.

```
class AtCheckerConfig(AtChecker):
    def __init__(self, inputFiles):
        AtChecker.__init__(self, inputFiles)
        self.add("pitch_angle", "", 1, "", "", "", "")
        self.add("roll_angle", "", 1, "", "", "", "")
```

Comment: Create a subclass. The subclass specifies the filters, number of atomic checkers, etc.. The class will affect at_checker.vhd

▷ self.add(input1, input2, count, filter1, filter2, rate1, rate2)

@ input1: First input to the at_checker
 @ input2: Second input to the at_checker, usually used for compare with @input1. We can leave it as a null string "".
 @ count: How many atomic checkers you want for this signal.
 @ filter1: Hardware filter you want to use for input1. The filter name should be the same as the hardware filter component
 @ filter2: Hardware filter you want to use for input2.
 @ rate1: Signal delta during each sampling clk for input1. Leave null if you want to monitor signal delta.
 @ rate2: Signal delta during each sampling clk for input2.


2.2 input.ast

Atomic assertion file. Specify the at_checker.vhd operation mode. For details, refer to **Performance Aware Hardware Runtime Monitors.pdf**.

e.g.

```
-16;0;0;+;>
1;0;0;+=
100;0;0;+;>
```

Each line specifies the configuration for one atomic checker block. Consider the structure of an



atomic checker, depicted in Figure.3, then each line in the configuration file reads as: C;n;m;+/-;f.

2.3 gen_uart_data.py

Generate uart data byte by byte. Requires .atc, .imem, .int and .dat as input. I suggest leave the .dat file empty for the demo purpose.

Parameters:

@ SETUP_DATA_WIDTH_extend_byte: .atc file configuration data width.
 @ SETUP_ADDR_WIDTH_extend_byte: .atc file configuration address width.
 @ DATA_BYTE_WIDTH_extend_byte: binary logged data bit width (each line width of logged_data.dat).
 These three parameters should be the same as in R2U2_pkg.vhd.

2.4 ser.py

1. serial.Serial()
e.g.

```

ser = serial.Serial(
    port='/dev/ttyUSB0',
    timeout=0,
    # baudrate=9600,
    # parity=serial.PARITY_ODD,
    # stopbits=serial.STOPBITS_TWO,
    # bytesize=serial.SEVENBITS
)

```

Comment: By default, it is 9600 baud rate 8N1 mode. You only need to specify the PC port that the UART is connecting to.


2. parameters: @ DATA_BYTE_WIDTH.extend_byte: (same as [gen_uart_data.py](#))

3 Demo Screenshot

Suppose all data is preprocessed properly. How are the screenshot sample:

1. Run [ser.py](#), it will wait for sensor input as in Figure 4.

Figure 4: Wait for input



```

/dev/ttyUSB0 is open.
Sending ATOMIC CHECKER, MONITOR configuration file.....
Configuration complete!


Enter log data in binary format.
(Insert "exit" to leave the application.)

data>>

```

2. Copy one line of data from [logged_data.dat](#) as sensor input:
The future time monitor output is shown in Figure 5.

Figure 5: Output sampel



```

data>> 0000000000000000000000001100111111111111111111110110
-----TIME STEP: 0-----
PC:0 = (False,0)
PC:1 = (False,0)
PC:2 = (False,0)

data>>

```

You can keep feeding sensor input and see output in each time step.